



## Adding an Uptime Indicator to your ANGEL Domain

You can easily add an uptime indicator to your college's ANGEL domain. These instructions describe how to add the indicator so that it appears on your ANGEL home page in the location shown below. The indicator also appears in the same spot on your ANGEL logon page, the Administrator Console, and the Preferences page:




The uptime indicator displays the percentage of ANGEL's uptime during the preceding seven days, as tracked by [Site24x7](http://Site24x7) using a logon test. The indicator can be clicked to view the following chart, which details ANGEL's uptime status during the period:

### Website Uptime Metrics by Site24x7



Click the More... link to display additional detail:



## Adding the ANGEL uptime indicator to your ANGEL domain

To add the uptime indicator:

1. Log on to ANGEL with Administrator privileges and navigate to the Administrator Console.
2. On the Institution tab, in the Domain Settings nugget, click the Configuration link for your domain.
3. On the Domain Configuration page, click the Display tab.
4. Copy the following code and paste it into the Site Header field:

**Note:** If the Site Header field already contains text or HTML, for best results you may need to experiment with where you paste the uptime indicator code in relation to the existing contents.

```
<table border="0" cellspacing="0" cellpadding="0" width="100%">
  <tbody>
    <tr>
      <td align="left">&nbsp; <a style="color: #ffffff; cursor: pointer;
text-decoration: none"
href="http://site24x7.com/login/status.do?execute=StatusReport&amp;p=TXNyNIA4E1
alhFv4vjSO6vGli3%2FehrEFDSxyGJeH66uVrP0Zur33sA%3D%3D&amp;u=true"><span
style="border-bottom: #dfa343 1px solid; text-align: center; border-left:
#dfa343 1px solid; padding-bottom: 0px; line-height: 12px; background-color:
#dfa343; text-indent: 2px; margin: 0px; padding-left: 0px; padding-right: 0px;
display: inline-block; font-family: Verdana; font-size: 9px; border-top:
#dfa343 1px solid; font-weight: bold; border-right: #dfa343 1px solid; padding-
top: 0px"><b>ANGEL uptime/week </b><b style="padding-bottom: 0px; background-
color: #ffffff; padding-left: 3px; padding-right: 2px; color: #000000; padding-
top: 0px"><script type="text/javascript" src="http://ext1.site24x7.com/website-
uptime.html?v=TXNyNIA4E1ZEzwwaKX%2BzTY9ajQOGEup8">
</script></b></span></a></td>
    </tr>
  </tbody>
</table>
```

5. Click the Save button and then navigate to the Home page. The indicator will be displayed in the approximate position shown at the top of page 1 of this document.